<u>คู่มือการตั้งค่าขนาดกระดาษใบจ่ายเงินเดือนสำหรับกระดาษต่อเนื่อง</u>

วัตถุประสงค์ *

เพื่อให้ผู้ใช้งานสามารถตั้งค่าขนาดกระดาษใบจ่ายเงินเดือนสำหรับกระดาษต่อเนื่อง 8.5 * 5.5 ก่อนทำการสั่งพิมพ์ใบจ่าย เงินเดือนลงฟอร์มดังกล่าวได้



วิธีการตั้งค่ากรณีเครื่องคอมพิวเตอร์เป็น Windows 7

เข้าเมนู All program > กดค้นหา Printer เลือก Devices and Printers หรือเข้าผ่าน Control Panel\Hardware and Sound\Devices and Printers

	tes and Printers
View	devices and printers
Add	a printer
Char	nge default printer
Shar	e printers
Char	nge advanced color management settings for displays, sca
100	
Netv	vork and Sharing Center
Netv	vork and Sharing Center r Management

จะปรากฎหน้าจอ Devices and Printers > ทำการเลือกเครื่องพิมพ์ ที่ต้องการเพิ่มขนาดกระดาย > จากนั้นเลือก Print server properties



🖶 Print Server P	roperties				•	
Forms Ports	Drivers S	ecurity Adva	anced			
Forms on:	Forms on: TSUPPORT165					
16K 6 3/4 Envelop 6 3/4 Envelop 8.5x5.5	pe pe 6 1/2 x 3	5/8 in		•	Delete Save Form	
Form name:	8.5x	5.5			1	
Define a new measuremen	Create a new form Define a new form by editing the existing name and measurements. Then click Save Form. Form description (measurements)					
Units:	Met	ric	English			
Paper size:		Printer are	ea margins:			
Width:	8.50in	Left:	0.00in	Тор:	0.00in	
Height:	Height: 5.50in Right: 0.00in Bottom: 0.00in					
OK Cancel Apply						

1. เลือก Create a new form 2. กำหนด Form name: เป็น 8.5 x5.5 3. กำหนดขนาด Form เลือก English Width: 8.50 Height: 5.50 4. กด Save Form 5. กด OK

คลิกเม้าส์ขวาที่เครื่องพิมพ์ จากนั้นเลือก > Printer properties > เลือก แถบ Device Settings > Manual Paper

Feed เลือกกระดาษที่สร้างไว้ (8.5 x 5.5) > กดปุ่ม Apply





คลิกเม้าส์ขวาที่เครื่องพิมพ์ เลือก > Printing Preferences

หน้าจอ Printing preferences เลือก Advanced...> Paper Size เลือกกระคาษ (8.5 x 5.5) > กดปุ่มOK

🖶 EPSON LQ-2180 ESC/P2 P	rinting Prefere	rences
Layout Paper/Quality User Orientation:	Defined Paper	r Extension Settings
EPSON LQ-2180 ESC/P2 Advanced Options	•	
EPSON LQ-2180 ESC/P2 Advanced Document Settings Paper/Output Paper/See: 0.555		
Cupy Councie <u>I Copy</u> Print Quality: <u>180 x 180 dots per inch</u> Document Options Advanced Printing Features: <u>Enabled</u> Pages per Sheet Layout: <u>Right then Down</u> Halftoning: <u>Auto Select</u> Print Optimizations: <u>Enabled</u> Print Features Print Quality: <u>High Speed - Default</u>	-	
		Advanced OK Cancel Apply
OK Cancel		

วิธีการตั้งค่ากรณีเครื่องคอมพิวเตอร์เป็น Windows 10

สามารถเข้าเมนู All program > กดค้นหา Printer เลือก Printers & Scanners

🕨 จะปรากฏหน้าจอ Devices and Printers > ทำการเลือกเครื่องพิมพ์ ที่ต้องการเพิ่มขนาดกระดาษ > จากนั้น เลือก

Print server properties

All Apps Documents Web More 🔻	Settings		- 🗆 X
Best match	A Home	Printers & scanners	
Printers & scanners System settings	Find a setting	Add printers & scanners	Troubleshoot your printer If you can't get your printer to work, try running the printer troubleshooter.
Settings		+ Add a printer or scanner	Open troubleshooter settings
☐ Add a prin ter or scanner >	Bluetooth & other devices		
Use the Prin t Screen key to launch screen snipping	凸 Printers & scanners	Printers & scanners	Related settings Print server properties
Find and fix problems with prin ting	🗇 Mouse		Run the troubleshooter
品 Let Windows manage my default printer >	Touchpad	G ^{Fax}	Help from the web
Change advanced color management settings for displays,	Typing	Microsoft Print to PDF	Downloading print drivers Scanning documents
Search the web	d ^p Pen & Windows Ink	Microsoft XPS Document Writer	Changing printer status
𝒫 prin - See web results >	AutoPlay	NPI327735 (HP Laser let P3010 Series)	Gethele
Apps (1)	D USB	Default	Give feedback
Folders (9+)		Open queue Manage Remove device	
Documents (4+)		Openhicte for Windows 10	
printers & scanners			

หรือเข้าผ่าน Control Panel\All Control Panel Items\Devices and Printers

จะปรากฏหน้าจอ Devices and Printers > ทำการเลือกเครื่องพิมพ์ ที่ด้องการเพิ่มขนาดกระดาษ > จากนั้น เลือก Print server properties

	I > All Control Panel Items >		ٽ ~
Adjust your computer's setti	ings		
🖶 Administrative Tools	Lo AutoPlay	Backup and Restore (Windows 7)	🍕 BitLocker Drive Encryption
💱 Color Management	Credential Manager	💣 Date and Time	🐻 Default Programs
🖑 Device Manager		🚱 Ease of Access Center	File Explorer Options
la File History	🗼 Fonts	lndexing Options	🊱 Internet Options
👡 Keyboard	🧼 Mail	Mouse	💐 Network and Sharing Cent
A Phone and Modem	🝞 Power Options	Programs and Features	🔊 Recovery
🔗 Region	is RemoteApp and Desktop Connections	Y Security and Maintenance	Sound
Speech Recognition	istorage Spaces	Sync Center	i System
Taskbar and Navigation	📕 Troubleshooting	🍇 User Accounts	💣 Windows Defender Firew
Windows Mobility Center	Work Folders		
- → → ↑ 📾 > Control Panel > All C	Control Panel Items > Devices and Printers	~	Search Devices and Printers
 Devices and Printers → ~ ↑ reprint Panel > All C Add a device Add a printer See what Add a printer See what 	Control Panel Items > Devices and Printers t's printing Print server properties Remove device	~	Search Devices and Printers
Devices and Printers → → → ↑ ♠ > Control Panel > All C Add a device Add a printer See wha Devices (2)	Control Panel Items > Devices and Printers t's printing Print server properties Remove device	~	Search Devices and Printers
Devices and Printers → → ↑ ♠ > Control Panel > All C Add a device Add a printer See what Devices (2) Rapoo 246 Wriefers Device Printers (9)	Control Panel Items > Devices and Printers It's printing Print server properties Remove device	~	C Search Devices and Printers
Devices and Printers → →	Control Panel Items > Devices and Printers It's printing Print server properties Remove device	, ,	− □ C Search Devices and Printers
Devices and Printers To be inter inters Add a device Add a printer See what Devices (2) AnyDesk Printer Fax Mice	Control Panel Items > Devices and Printers t's printing Print server properties Remove device Print server properties Remove device Remove	SheNate for Windows 10 OneNate for Windows 10 Or PDF Architect 6	C Search Devices and Printers C PDFCreator

	2.11010 0		anced		
Forms on:	TSUPPO	RT165			
16K				<u> </u>	Delete
6 3/4 Envelop	be 6 1/2 x 3	5/8 in			
8.5x5.5				-	Save Form
	0.5.4				7
Form name:	0.5X	2.2			
	<u> </u>				
Casta a a		/			
🔽 Create a n	ew form	/			
☑ Create a n Define a new	ew form	liting the exis	sting name ar	nd	/
Create a n Define a new measuremen	ew form form by ed ts. Then cli	liting the exis ck Save Form	sting name ar 1.	nd	/
Create a n Define a new measuremen	ew form form by ed ts. Then cli ntion (mea	liting the exis ck Save Form	sting name ar n.	nd	/
Create a n Define a new measuremen Form descri	ew form form by ed ts. Then cli ption (mea	liting the exis ck Save Form surements) –	sting name ar n.	nd	/
Create a n Define a new measuremen Form descrij Units:	ew form form by ed ts. Then cli- ption (mea: © Met	liting the exis ck Save Form surements) – ric	sting name ar n. @ English	nd	/
Create a n Define a new measuremen Form descrij Units: Paper size:	ew form form by ed ts. Then cli ption (mea: © Met	liting the exis ck Save Form surements) – ric Printer are	sting name ar n. © English ta margins:	nd	/
Create a n Define a new measuremen Form descrip Units: Paper size: Width:	ew form form by ed ts. Then cli ption (mea @ Met 8.50in	liting the exis ck Save Form surements) – tric Printer are Left:	sting name ar n. English sa margins: 0.00in	nd Top:	0.00in
Create a n Define a new measuremen Form descrip Units: Paper size: Width: Height:	ew form form by ed ts. Then cli ption (mea 0 Met 8.50in 5.50in	fitting the exis ck Save Form surements) tric Printer are Left: Right:	sting name ar n. English English 0.00in 0.00in	Top: Bottom:	0.00in 0.00in
Create a n Define a new measuremen Form descrip Units: Paper size: Width: Height:	ew form form by ed ts. Then cli ption (mea 0 Met 8.50in 5.50in	diting the exis ck Save Form surements) – tric Printer are Left: Right:	esting name ar n. English English English 0.00in 0.00in	Top: Bottom:	0.00in 0.00in

1. เลือก Create a new form 2. กำหนด Form name: เป็น 8.5 x5.5 3. กำหนดขนาด Form เลือก English Width: 8.50 Height: 5.50 4. กด Save Form 5. กด OK

คลิกเม้าส์ขวาที่เครื่องพิมพ์ จากนั้นเลือก > Printer properties > เลือก แถบ Device Settings > Manual Paper

Feed เลือกกระดาษที่สร้างไว้ (8.5 x 5.5) > กดปุ่ม Apply



- - * K + Hardware and Sound + Devices and Printers P + +++ Add a device Add a printer See what's printing Manage default printers Print server properties - 12 0 Devices (3) 2.4GHz 2way RF Receiver TSUPPORT165 USB Keybo Printers and Faxes (9) Open Open in ne See what's printing EPSON LQ-300+ /II ESC/P 2 EPSON LQ-2090 ESC/P 2 Ver 2.0 Microsoft XPS EPSON LC Set as default printer LaserJet ESC/ CL6-Acc P3005 **Document Writer** Printing preferences PCL6-Payroll Create shortcut Troubleshoot Remove devic Properties OneNote 2007 EPSON LQ-2180 ESC/P2 State: 🥑 Default Status: 0 document(s) in queue Model: EPSON LQ-2180 ESC/P2 Category: Printer
- คลิกเม้าส์ขวาที่เครื่องพิมพ์ เลือก > Printing Preferences

➤ หน้าจอ Printing preferences เถือก Advanced...> Paper Size เถือกกระดาษ (8.5 x 5.5) > กดปุ่มOK

	EPSON LQ-2180 ESC/	/P2 Printing Preferer	nces	X
L.	ayout Paper/Quality Orientation:	User Defined Paper	Extension Settings	
EPSON LQ-2180 ESC/P2 Advanced Options	Portrait	· ·		
EPSON LQ-2180 ESC/P2 Advanced Documen Paper/Output Paper/Size 85555 Copy Counc 1 Copy	t Settings			=
Graphic Print Quality: <u>180 x 180 dots per inch</u> Print Quality: <u>180 x 180 dots per inch</u> Advanced Printing Features: <u>Enabled</u> Pages per Sheet Layout: <u>Right then De</u> Halftoning: <u>Auto Select</u> Print Optimizations: <u>Enabled</u> Print Features Print Quality: <u>High Speed - Default</u>	<u>2000</u>			
			0	Advanced Cancel Apply
[OK Canc	el		

** หมายเหตุ การแอคฟอร์มกระคาษต้องคำเนินการที่เครื่องคอมพิวเตอร์ที่ต่อปริ้นเตอร์อยู่ โดยตรงเท่านั้น

**<u>แนะนำช่องทางการติดต่อฝ่ายบริการ</u> :

กรณีที่ด้องการสอบถามเพิ่มเติม ท่านสามารถแจ้งรายละเอียดที่ต้องการทราบเพิ่มเดิมได้ทาง Line@ ของฝ่ายบริการ คือ @businessplus_pr ซึ่งจะมี เจ้าหน้าที่ให้บริการ ดังนี้

- ในเวลาทำการ วันจันทร์ ถึง วันศุกร์ ตั้งแต่เวลา 08.30 น. 17.30 น.
- นอกเวลาทำการ วันจันทร์ วันศุกร์ ตั้งแต่เวลา 17.30 น. 22.00 น. และ วันเสาร์ วันอาทิตย์ วันหยุดนักขัตฤกษ์ ตั้งแต่เวลา 08.30 น. 22.00น.